

Monobloc setup guide

1. "monoblock 0.0.1.zip" Select the folder you want to use and unzip it.
2. execute yoshop_retail_windows.exe
3. select server DEV-KZ and log in
4. select a Store
5. accept the terms and conditions
6. start the app

Close App

-Alt-F4 Or TaskManager kill process

Remove Store Info - To set up a new store

- Delete the ".dart_tool" folder in the unzipped folder
- C:\Users\%userprofile%\Documents
 - *.hive
 - *.lock
 - Delete all extensions hive, lock

Connet K9 Device

1. Open Drawer -> select setting

- ×
- Dashboard
- Pos
- Task
- Employee
- Order
- Warehouse
- Reports
- Return
- Revision

Cashier: Emp1

Board Sales 00 ₹ Sales

Balance 0,00 ₹ -17.0 Quantity

Daily

	Name	Amount
--	------	--------

Daily

ne	hours	Amount
----	-------	--------

debug

2. Select System setting

☰ Settings

Language

Synchronization

System settings

Log out

Cashier: Emp1



Save


Reset

← Back






3. External payment setting

- Enable external payment application
- Input K9 Device (Yoshop Pay 1.6.4~)

 **Settings**

Cashier: Emp1



Country settings

Interface language

ENG

Check language

ENG

POS type

Retail

Currency

KZT

Use auto open shift

☒

Barcode scanner type

Back camera

External payment settings

Use external payment application


☒

External payment application host (IP)


192.168.50.3

[Connect](#)


Log out



3-1. If you've entered an incorrect address or Pay is out of date, you'll see a warning.



3-2. Connected Device






4. Save information

yoshop_retail_windows

Settings

Cashier: Emp-T



SaveResetBack

Language

Synchronization

System settings

Devices

Barcode scanner typeBack camera

External app settings

Use external payment app

External payment app host (IP)192.168.50.17Connect

Use external printer app

printerModelSERIAL




PortCOM10

5-1. Print (Externalprint - K9 print)

yoshop_retail_windows

Settings

Cashier: Emp-T



DEMO

Save

Reset

← Back

Language

Synchronization

System settings

Devices

Barcode scanner type

Back camera

External app settings

Use external payment app

External payment app host (IP)

192.168.50.17

Connect


Use external printer app

External payment app host (IP)

192.168.50.17

Connect

Log out



5-2. Print -serial print

yoshop_retail_windows

Settings

Cashier: En

Barcode scanner type: Back camera

External app settings

Use external payment app: ☒

External payment app host (IP): 192.168.50.17

Use external printer app: ☐

printerModel: SERIAL

Port: COM10

Speed: 57600

paperSize: 3 inch

Log out

Device Manager

File Action View Help

DESKTOP-7V3J63B

- > Audio inputs and outputs
- > Batteries
- > Biometric devices
- > Bluetooth
- > Cameras
- > Computer
- > DellInstrumentation
- > Disk drives
- > Display adapters
- > Firmware
- > Human Interface Devices
- > Imaging devices
- > Keyboards
- > Mice and other pointing devices
- > Monitors
- > Network adapters
- ✓ Ports (COM & LPT)
 - USB 직렬 장치(COM8)